

Photo Story 3 Creating Your Photo Story

Contents

Photo Story 3.....	3
Creating Your Photo Story	3
Selecting Your Photographs	3
To Select and Import Your Photographs.....	3
Removing Black Borders.....	4
Viewing and Arranging Photos in the Film Strip.....	5
Editing Photos.....	6
To Edit a Photo	6
To Save Your Photo Story as a Project	7
To Add Titles to Your Photos.....	8
Narrate Your Pictures and Customize Motion	9
Customizing Motion.....	9
Motion.....	9
Duration.....	10
Transition.....	10
Narrating Your Pictures	10
Configuring Your Microphone.....	11
Narrating	11

Photo Story 3

Adding Background Music	12
Previewing Your Story.....	13
Saving Your Story	13
Choosing What You Want to Do with Your Photo Story.....	16
To Save Your Story on Your Computer and Create a Video CD (VCD) or DVD	16
To Save Your Story on Your Computer and Attach It to an E-mail Message	16
Other Options.....	17
Maintaining Your Photo Story Settings	17
Editing an Existing Photo Story	17
Viewing Your Photo Story	18

Photo Story 3 Creating Your Photo Story

Selecting Your Photographs

To create your new Photo Story you first need to select the photos you want to use. It might be a good idea to copy or move these photographs to a new folder on your computer.



Each story can contain up to 300 photos.

Most photos will be .jpg files but all the following file types are supported by Photo Story 3: .bmp, .dib, .eps, .gif, .jhif, .jpe, .jpeg, .jpg, .pcd, .pcx, .png, .psd, .rle, .tga, and .tif.

After you import your pictures, you can arrange them on the Photo Story film strip in the order you want them to be displayed. Then you can use the editing tools to edit, enhance, rotate, and crop your pictures.

To Select and Import Your Photographs

1. Open Photo Story 3.
2. Make sure the BEGIN A NEW STORY radio button is selected and click NEXT.
3. On the next window click IMPORT PICTURES.
4. This will open the FILE BROWSER window,



which is similar to the My Computer window.

It shows all your folders on the left hand side. If you click on a folder the photographs in that folder appear on the right hand side. The photos are normally shown in thumbnail form. You can move the slider at the top right to change the size of the thumbnails. Move the slider button to the right (+) to increase the thumbnail size and to the left (-) to decrease the size. You also have the option to change from thumbnail view to DETAILS or LIST view by clicking on the VIEW MENU button (to the left of

the slider).

The LIST option shows you a list of photographs in the folder, giving only the file name of the photo.

Photo Story 3

The DETAILS option shows the list of photos, giving file name, photo dimensions, file size, date modified and date taken.

5. To select your photos do one of the following:
 - To select a photo click on it → OK.
 - To select a number of contiguous photos click on the one at the top left of the group you want to select, hold down the SHIFT button and now click on the photo at the bottom right of the group you want to select → OK.
 - To select a group of non-contiguous photos click on the first one, hold down the CTRL button, click on each photo you want to select → OK.
 - To select all the photos, or a large group of photos, click and hold down the RIGHT mouse button, starting in the white space to the right of the photos. Now drag the cursor left and down over the photos you want to select → OK.
6. You can import more photos by clicking on IMPORT PICTURES again and repeating the process from the same folder or from another folder.

Note: If you import a second batch of photos these will be added at the end of the story line.

Removing Black Borders

In Photo Story photos are displayed in a 4:3 aspect ratio. If some of your photos are not in this aspect ratio they will appear with black borders filling the remaining space.

If you want Photo Story to remove these black borders you can do this in the *Import and Arrange Your Pictures* window.




1. Click on the REMOVE BLACK BORDERS icon, to the right of the photo preview window. 
2. Photo Story now identifies, in turn, each photo with a black border. The first photo appears in the REMOVING BLACK BORDERS window. There is a BEFORE (left) and an AFTER (right) window. The Before window shows the original photo with the area recommended by Photo Story selected. The After window shows the result of editing the photo down to the selected area. 
3. You have a number of options
 - YES If you select this option you are accepting the suggested editing. The photo will appear as shown in the AFTER window on the right. Photo Story will then move on to the next photo with black borders and you can repeat the process.

Photo Story 3

- YES TO ALL If you select this option you are accepting the suggested editing for all photos with black borders, without viewing them.
 - NO Choose this option if you do not want to accept the suggested edit. Photo Story will then move on to the next photo with black borders.
 - CANCEL This option closes the Remove Black Borders window and returns you to Photo Story.
4. You can also make changes to the suggested editing by moving or re-sizing the selected area before accepting it.
 5. To change the selected area place the cursor inside the selected area of the photo in the BEFORE window. The cursor turns into a four- sided arrow. Click and drag the cursor to select a different part of the photo. You can observe the changes you make in the AFTER window.
 6. To resize the selected area hold the cursor over one of the handles at the corners and the middle of each side in the BEFORE window.
Click and drag in or out to resize.
 - Dragging the top left handle will resize by changing the top and left sides, while retaining the 4:3 aspect ratio.
 - Dragging the top right handle will similarly resize changing the top and right sides.
 - The other two corner handles similarly resize by changing the contiguous sides.
 - Dragging any of the four middle handles will resize by changing all sides except the one opposite the handle, and, once again the 4:3 aspect ratio is retained.
 - **Note:** None of the above changes affects your original folder where it is stored on your computer.



Viewing and Arranging Photos in the Film Strip

In the *Import and Arrange Your Pictures* window you can view your photos and change their order.

When you import your photos the first photo appears in the preview window on the left. You can view the next photo by clicking the NEXT PICTURE arrow (bottom right) or the previous photo by clicking on the PREVIOUS PICTURE arrow (bottom left).

You can also view any photo by scrolling across the scroll bar at the bottom of the film strip.

1. To change the order of the photos click on a photo in the film strip and drag it to a new location. If you drop a photo over an existing photo, Photo Story will place it to the left of that photo if you have




Photo Story 3

dragged it towards the left and will place it to the right of that photo if you have dragged it to the right.

2. To move a photo one place back or forward right-click on it → MOVE BACK or MOVE FORWARD.

OR

Select it and click on the MOVE BACK or MOVE FORWARD arrow to the right of the film strip.



3. To remove a photo from the Photo Story right-click on it → DELETE.

OR

Select it and click on the DELETE button to the right of the film strip.



Note: This does not delete your original photo from your computer.

Editing Photos

In the *Import and Arrange Your Pictures* window you can do some basic editing on your photos. If you want to do more detailed editing it might be better to have the photo editing done before importing the photos into Photo Story.

If you want to do some quick and basic editing then the following options will be useful.

To Edit a Photo

1. Select the photo you want to edit from the film strip. Your photo appears in the preview window on the left. You can now use one of the five buttons



under the preview window to edit the

photo.

2. Click on the CORRECT COLOR LEVELS button to adjust colour the colour in your photo. This is an automatic adjustment and you do not have control over it.
3. Click on CORRECT RED EYE to remove red eye from your photo. This too is automatic and you do not have control over it.
4. Click on ROTATE COUNTERCLOCKWISE or ROTATE CLOCKWISE to rotate your photo. If photos need to be rotated it is a good idea to do this before you remove the black borders. Very often a rotated photo will no longer have a 4:3 aspect ratio and therefore will have black borders.
5. The EDIT button allows you to make a number of additional edits. When you click on EDIT the Edit Pictures window appears.

Photo Story 3

- Under the ROTATE AND CROP tab you again have the option of rotating the photo.


You can also crop the photo.

- To crop your photo first click in the CROP check box.
- Your photo appears greyed out, with a rectangular visible area selected.
- Just as in the Remove Black Borders option, you can use the corner and side handles to adjust the size of the selected area.
- You can also place the cursor within the selected area, where it will become a four-sided arrow.
- Now click and drag the selected area to show a different part of the photo.
- Click SAVE to perform the crop or click RESET if you do not want to crop the photo.

- Under the AUTO FIX tab you can choose CORRECT CONTRAST, CORRECT COLOR LEVELS or CORRECT RED EYE by selecting the ON radio button in each case. Once again click SAVE to make the changes and RESET to reject them.



- Under the ADD EFFECT tab you have a range of effects, e.g. black and white, sepia, etc. That you can add. There is also a check box to allow you to add the chosen effect to all photos in your photo story, if you wish. (If you choose this option and there is a large number of photos in your photo story, this may take some time.) Once again click SAVE to make the changes or RESET to reject them.



Note: When you click the RESET button this returns the photo to its original form and you lose all edits performed under any of the Edit Pictures tabs.

Note: When you return to the *Import and Arrange your Pictures* window any edited photos will appear dimmed and there will be a symbol, or symbols underneath to show the edits performed.

Note: Any edits made to your photos in Photo Story will not affect your original photos stored on your computer.

To Save Your Photo Story as a Project

You can save your photo story as a project at any time. This means that you can return later and edit it. If you do not save it as a project you will not be able to edit it later. It is a good idea to save early and often.

- Click on SAVE PROJECT and this opens the SAVE AS window.


Photo Story 3

2. In the SAVE IN window choose a location for your project. By default Photo Story will choose to save it in your My Videos folder. However, you can choose your own location.
3. Some people prefer to have all their photos for a photo story in one folder and to save the project in this folder also. This means that if the folder is later moved or renamed Photo Story can still locate the photos for the photo story.
4. By default Photo Story projects are saved as .wp3 files. This allows Photo Story to open them at a later date for editing.

To Add Titles to Your Photos

You can add titles to your photos or you can add a title photo to the beginning of your story. When you add titles to photos they are then static photos and you cannot add movement, zooming or panning effects to those photos.

1. If you are still in the *Import and Arrange Your Pictures* window click the NEXT button.



2. This brings up the *Add a Title to Your Pictures* window.
3. Select the photo to which you wish to add the title. It appears in the preview window on the left.
4. If you wish to also add an effect to this photo click the drop-down list on the EFFECT menu under the preview window and select an option.
5. Click in the textbox on the right and type the text you want. Press ENTER to create a new line of text.
6. Click on the FONT button at the top left of the textbox and from the font window choose the desired Font, Style, Size and Colour → OK.
7. Choose the text alignment (horizontal) – ALIGN LEFT, CENTER HORIZONTALLY or ALIGN RIGHT from the text alignment buttons at the top centre of the textbox.
8. Choose the text alignment (vertical) – ALIGN TOP, CENTER VERTICALLY or ALIGN BOTTOM.
9. Continue to select other photos to which you wish to add titles. Any changes you make can be checked in the preview window on the left.

Note: You need to be careful that the text colour you choose for your titles, contrasts with the colours in the photo and that the text location does not ruin the effect of the photo.

Tip: If you want to have a title photo at the beginning of your story it might be a good idea to have a blank white (or other coloured) photo. You can photograph a

Photo Story 3

white sheet of paper and use this as a photo or create a white image in Paint Shop Pro or other image editing software.

When you have finished adding titles to your photos, click on the NEXT button to move on to the ***Narrate Your Pictures and Customize Motion*** window.

Narrate Your Pictures and Customize Motion

In this window you can narrate up to five minutes for each photo and keep notes for each photo. By default Photo Story will apply a random zoom or pan effect to each photo and display each photo for five seconds. You can manually set the panning and zooming effects for your photos and the duration for which each photo is displayed. You can also set transitions and transition timings.

Customizing Motion

Motion




1. Click the CUSTOMIZE MOTION button under the preview window.
2. The ***Customize Motion*** window opens.
3. Under the MOTION AND DURATION tab you can specify the starting position and end position of each photo or accept the suggested positions.
4. To select the start and end positions click the SPECIFY THE START AND END POSITION OF MOTION check box. You can now set the start position and how much of the photo is shown at the start (left preview window). You can move or resize the selected area as you did when removing black borders. Now you can do the same for the end position (right preview window).
5. Underneath the preview windows Photo Story shows the starting and end position of this photo on your photo story timeline. The default display time for each photo is 5 seconds. It also shows you the start and end dimensions of the displayed photo.
6. You can also set the start position of this photo to be the same as the end position of the previous photo by ticking the relevant check box. (This option is not available for the first photo.)
7. You can also specify that the start and end positions for this photo are the same. This will mean that there is no pan or zoom effect.

Photo Story 3

Duration



1. You can select SET DURATION AUTOMATICALLY. The default time is 5 seconds per photo.
2. You can also specify the length of time for which each photo is displayed. Click the NUMBER OF SECONDS TO DISPLAY THE PICTURE check box and enter the number of seconds in the box.
3. It is a good idea to preview these effects before you complete your settings. Click on PREVIEW and a preview of your photo story appears in a small window, showing the elapsed time. You can close the preview at any time by clicking the X at the top right corner.



Transition

By default a transition is inserted between photos in a photo story. Under the TRANSITION tab you can select which photos you want to start with a transition, select a transition and select the duration for the transition.

1. If you want a photo to start with a transition click in the START CURRENT PICTURE USING A TRANSITION check box. The three small preview windows will show the previous photo, the transition and the current photo.
2. You can choose from a range of transitions. Scroll down the transitions window for more options. Click on a transition to see a preview.
3. Now you can decide to SET TRANSITION DURATION AUTOMATICALLY (the default is one second) or to specify NUMBER OF SECONDS TO DISPLAY TRANSITION.
4. Now click SAVE to accept the choices you have made or RESET to reject them. Clicking RESET discards all edits made in the *Customize Motion* window.
5. You can click on PREVIEW at any time to preview your work.
6. When you have finished with this transition you can click on the GO TO NEXT PICTURE or GO TO PREVIOUS PICTURE arrows at the bottom of the window to continue editing.
7. When finished customizing motion click CLOSE.



Narrating Your Pictures

On the Narrate your pictures and customize motion page, you can

- record up to five minutes of narration per photo
- narrate the photos in any order
- type notes for each narration
- delete a narration and record it again.

Photo Story 3

Note: Deleting a narration does not delete any of the other edits you have made to your photos.

Configuring Your Microphone

Before you start narrating your photos, click on the Configure Microphone and Set Recording Volume button. This will activate a wizard to test your microphone.



1. Step 1 identifies your computer's sound hardware. Click NEXT.
2. Step 2 tests your computer's sound hardware and moves on to Step 3.
3. Step 3 allows you to test your microphone by reading a given paragraph and to make adjustments to the microphone volume and balance, using the VOLUME button. Click NEXT when finished.
4. Step 4 allows you to test your speakers or headphones by reading a given paragraph and to make adjustments using the VOLUME button. Click NEXT when finished.
5. Click FINISH to complete the microphone configuration.

It is important to ensure that your microphone is working correctly and that the volume is set properly. If you make a recording and are not happy with the sound quality you can go back and reconfigure your microphone. On computers with built-in microphones the sound quality may vary from one recording to another, depending on extraneous noise levels.


Note: If your microphone is unplugged when you are recording your narration, Photo Story may not detect that this and will not display an error message.

Narrating

1. Select the photo onto which you want to record the narration.
2. Click on the RECORD NARRATION button.
3. Speak your narration into the microphone.
4. You can record up to five minutes for each photo.
5. The length of the narration is shown to the right of the Delete Narration button.
6. To end the narration click on the STOP RECORDING button. You can recommence narration on that photo by clicking on the RECORD NARRATION button again, provided you have not selected another photo.
7. To add narration to another photo, select the photo and record as above.



Photo Story 3


- To delete narration from a photo select the photo and click on the DELETE NARRATION button. You can then record a  new narration.
- Deleting a narration does not delete any other edits on the photo but it may change the length of time a photo will be displayed.
- A photo with a narration will appear dimmed on the film strip and will have a narration symbol displayed at the bottom left of the photo. The length of time the photo will be displayed is shown over the photo on the film strip.
- It is a good idea to preview your photo story after recording a narration so that you can check volume levels and sound quality. The preview will begin from the photo that is selected in the film strip.

Adding Background Music

You can add background music that plays during your photo story and even select different music to play for different photos or groups of photos.

You can select music from your computer or use Photo Story's prerecorded music.

- If you are still in the **Narrate Your Pictures and Customize Motion** window click NEXT.
- This brings up the **Add Background Music** window.
- Click on the photo where you want the music to begin.
- Click on CREATE MUSIC. This opens the CREATE MUSIC dialogue box.
- Select from the GENRE, STYLE, BANDS and MOODS menus.
- Select the TEMPO and INTENSITY.
- You can click on the PLAY/PAUSE button to listen to your choice and click the PLAY/PAUSE button again to stop the music.
- When you are satisfied click OK.
- You will now return to the ADD



BACKGROUND MUSIC window. You will notice that the photo you selected now has a music symbol underneath it to show that it is now the anchor photo for that piece of music. There is also a coloured music strip over the photos for which the music will be played. This strip shows the title of the music. The music will play automatically from that photo to the end of the photo story or until it meets another anchor photo, with a different piece of music or until the music ends.

Photo Story 3

10. If you want to add another piece of music to a later group of photos select the first photo in the group and repeat the process above.
11. If you want some photos to display in silence click on CREATE MUSIC and under GENRE choose SILENCE. This might be useful where you wished to narrate onto some photos.
12. If you wish to add a piece of music from your computer click on SELECT MUSIC. The OPEN dialogue box appears. Locate the music on your computer and click OPEN. The music file can be in Windows Media Audio (WMA), MP3, or WAV format.
13. To delete background music, click on the anchor photo for that piece of music and then click DELETE MUSIC. You can also right click on the photo, select music and then DELETE. If you click on a photo other than the anchor photo you can also delete the music, but be careful because this too will delete the entire piece of music.
Note: Be careful here because if you right-click on a photo and click DELETE you will delete both the photo and the music!
14. Finally you can set a volume level for your background music.

Previewing Your Story

You can preview your photo story in the *Narrate Your Pictures and Customize Motion* window, in the *Customize Motion* window, and in the *Add Background Music* window. When you click on the PREVIEW YOUR STORY button the Preview window opens.

In the Preview window you have the following options:

PLAY / PAUSE to play your entire story or to play part of the story, starting with a selected photo.



PAUSE to pause the playback.

STOP to stop playing the story.

GO TO PREVIOUS PICTURE

GO TO NEXT PICTURE


SEEK SLIDER to view your photo story from a particular point. Drag the slider left or right to move back or forward to a new point in your photo story.

CLOSE to close the Preview window.

Saving Your Story

Photo Story 3

You can select from a range of activities for your photo story. The settings for your story depend on the activity you select. You can save your story to play on your computer, to send in an email or to play on a portable device such as a Pocket PC or a Smartphone. For this tutorial we will concentrate on saving your photo story to play on your computer.



1. If you are still in the **Add Background Music** window click on NEXT. This brings up the SAVE YOUR STORY window.
2. In the ACTIVITIES window select SAVE YOUR STORY FOR PLAYBACK ON YOUR COMPUTER.
3. Under FILE NAME click on BROWSE to find the location where you want to save your photo story.
4. Type a file name for the story and click SAVE.
5. Under QUALITY SETTINGS Photo Story gives a recommended profile and description. The profile might be 640 X 480, which means that it will display at 640 pixels by 480 pixels. The description gives the computer processor speed and RAM for which this profile would be appropriate.
6. Click on SETTINGS and in the Settings dialogue box click on the PROFILE drop down menu to see alternative profiles.
7. Select one of the profiles and click OK. If you select a profile that requires a computer that is more powerful than your computer, you will get a message stating that Photo Story cannot create the story. You can try selecting another profile or try freeing up disk space on your hard drive.
8. In the Save Your Story window click NEXT.
9. This opens the BUILDING YOUR STORY dialogue box and Photo Story builds your story in four steps:
 - Building story;
 - Generating music;
 - Mixing audio;
 - Generating video.
10. This can take some time, depending on the speed of your computer, the number of photos in the story and the amount of music you have added.




Photo Story 3

11. When the building process is complete *Completing Photo Story 3 For Windows* appears. This gives the name, location and file size of your story. Photo Story also automatically adds a link to your story in your Windows Media Player library.
12. There is an option to VIEW YOUR STORY, to CREATE ANOTHER STORY or to EXIT Photo Story.
13. After you select the profile or quality settings and save your story it is a good idea to preview your final story to ensure that the quality of the video playback is acceptable. If the video quality is poor you can return to the Save Your Story window and select a different profile to use different video quality settings.
14. The profile you select enables you to choose from a range of video resolutions. The audio quality is set by default, depending on profile selected. Higher-quality video is accompanied by higher-quality audio. The better the video quality, the larger the size of the file and the more system resources are required to save and play it.
15. If you intend to share your story with others you might need to think of the computers they will use to view your story and change the profile and quality settings accordingly.
16. One more important option here is SAVE PROJECT and it is a good idea to do so. This will save the finished photo story as a project, which you can edit later. When you click on SAVE PROJECT the SAVE AS dialogue box opens. The file name will be that which you used in your earlier project save.
17. If you want to just save the latest version of your project under the same name click SAVE. You will be prompted that this file already exists and asked if you wish to replace it. Photo Story will then update your project.
18. If you want to save the latest version of your project under a new name or in a new location type a new file name, select a new location and then click SAVE.
19. You can now EXIT Photo Story.

Note: For certain activities, such as sending the story in an e-mail message, you cannot save the story, give it a file name or specify a location until *Completing Photo Story 3 for Windows* is displayed. If you choose to send the story in an e-mail message in the *Save Your Story* window, *Completing Photo Story 3 for Windows* also gives two additional options:

- Save a copy of your story to your computer or
- Continue to mail your story.

Select your preferred option.

Photo Story 3

Choosing What You Want to Do with Your Photo Story

You have already learned how to save your story for playback on your computer. Below are some other options available in Photo Story.

To Save Your Story on Your Computer and Create a Video CD (VCD) or DVD

1. In the Settings dialogue box, select the profile that is recommended for your VCD or DVD player.
2. For Video CDs and DVs, PAL (Phase Alternating Line) is the European and Australian Setting. (France and Russia use a different system, but it should be compatible with PAL.)
3. NTSC (National Television System Committee) is the standard format for The United States, Canada, Japan and a number of other Asian and South American countries.
4. Then import the story into another VCD or DVD authoring program that supports WMV files and burn the story onto a CD or DVD.

To Save Your Story on Your Computer and Attach It to an E-mail Message

1. In the Settings dialogue box, select one of the three profiles that are recommended for e-mail.
2. If possible, Photo Story compresses your story to be one megabyte (MB) or less because some e-mail service providers do not allow users to send files that are larger than 1 MB.
3. However, you can select a profile that results in a story that is more than 1 MB.
4. The three profiles give different display size options. The larger the display size the larger the file size. (For example, a story that takes up approximately 14MB saved at 640 X 480 would take up approximately 4MB saved for email at 320 X 240; 2.3 MB saved at 240 X 180 and 2 MB saved at 160 X 120).
5. After Photo Story builds your story, on the *Completing Photo Story 3 for Windows* page, click CONTINUE TO E-MAIL YOUR STORY.
6. If your e-mail program is configured, Photo Story opens an e-mail message with your story attached.
7. If your e-mail program is not configured, you can save your story by clicking SAVE YOUR STORY, on the *Completing Photo Story 3 for Windows* page.

Photo Story 3

8. You can then send the story in an e-mail message after you configure your e-mail program.
9. It is probably better to save your story on your computer in e-mail profile and send it as an attachment later.

Other Options

You can also save your story

- for playback on a Pocket PC with Windows Media Player 10 Mobile.
- for playback on a Smartphone with Windows Media Player 10 Mobile.
- for playback on a Portable Media Center.

In each case Photo Story builds your story using a profile that is appropriate for your device, and then saves the story to the location on your computer that you specified.

You must use another program to copy the story to your device.

Maintaining Your Photo Story Settings

When you begin a new project Photo Story maintains many of the settings from your previous story.

This makes it easier to create multiple stories.

The settings maintained include the folders from which you previously imported photos and the background music you added.

Editing an Existing Photo Story

1. Open Photo Story 3 for Windows.
2. On the Welcome to Photo Story 3 for Windows page, click EDIT A PROJECT.
3. The Open dialogue box appears. Locate and select the file name of the story you wish to edit. Click OPEN. (By default, project files are saved in your My Videos folder but you may have saved your story in another folder).
4. Proceed with the editing changes you wish to make.
5. In the Save Your Story window, select an activity for your story.
6. Type a new file name for the story if you do not want to replace your existing story.
7. If you also want to save your revised story as a new project file, on the SAVE PROJECT button.
8. Type a new file name for the story if you do not want to replace your existing project.
9. Click NEXT.

Photo Story 3

10. If you do not enter a new file name for your edited story or project you will be prompted that this file already exists and asked if you want to replace it.
11. Click YES if you want to replace existing files or click NO if you want to save the story or project under new file names.

Viewing Your Photo Story

Windows XP is required to use Photo Story 3 for Windows to create photo stories, but you do not need it to view stories.

Any computer with Windows 98 SE, Windows Millennium Edition or Windows 2000 can also be used to view photo stories, using any program, e.g. Windows Media Player version 7 or later, that can play Windows Media Video (WMV) files. If you try to play a photo story using an earlier version than Windows Media Player 10 you will be prompted to upgrade Windows Media Player.

Use one of these methods to view your photo story:

1. Open Photo Story 3 for Windows.
2. Click on PLAY A STORY.
3. Locate and select the story you wish to play and click on PLAY.

OR

1. Open Windows Media Player 10.
2. Click on LIBRARY on the top menu bar.
3. Expand PLAYLISTS by clicking on the + sign in front of Playlists.
4. Click on PHOTO STORY 3 PLAYLIST.
5. Double-click the story you want to play.

OR

1. Open Windows Media Player 10.
2. Click on LIBRARY on the top menu bar.
3. On the LIBRARY drop-down menu select VIDEO.
4. Expand LIBRARY on the left hand side by clicking on the + sign in front of Library.
5. Click on ALL VIDEO.
6. Double-click on the story you want to play.